

```
santa-sb# conf t
```

Enter configuration commands, one per line.

Edit with DELETE, CTRL/W, and CTRL/U; end with CTRL/Z

```
interface serial 1
```

```
encapsulation ppp
```

```
^Z
```

```
santa-sb# sh int s 1
```


Serial 1 is administratively down, line protocol is down

Hardware is MCI Serial


MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255

Encapsulation PPP, loopback not set, keepalive set (10 sec)


**Figure 1**  
**(Prior Art)**



**Figure 2  
(Prior Art)**



**Figure 3**



**Figure 4**

5.1 <filename>info.dat  
704 { 1) frLportCnfEntry 1.3.6.1.4.1.351.100.4.2.1.1.1 Aggregate not-accessible

5.2 <filename>.defs

706 {	1) frLportCnfEntry	frLportCnfTable.1	Aggregate	not-accessible	mandatory
	2) %ei frLportCnfEntry	"frLportSlotIndex"		frLportPortIndex"	
708 {	3) frLportSlotIndex	frLportCnfEntry.1	INTEGER	read-only	mandatory
	4) %er frLportSlotIndex	1 32			
710 {	5) frLportPortIndex	frLportCnfEntry.2	INTEGER	read-only	mandatory
	6) %er frLportPortIndex	1 32			
	7) frLportClockType	frLportCnfEntry.3	INTEGER	read-write	mandatory
712 {	8) %ev frLportClockType	normal	1		
	9) %ev frLportClockType	looped	2		
	10) %ev frLportClockType	none	3		
	11) frLportOperStatus	frLportCnfEntry.4	INTEGER	read-only	mandatory
	12) %ev frLportOperStatus	inActive	1		
714 {	13) %ev frLportOperStatus	active	2		
	14) %ev frLportOperStatus	looped	3		
	15) %ev frLportOperStatus	failed	4		
716 {	16) frLportPolVerTmr	frLportCnfEntry.5	INTEGER	read-write	mandatory
	17) %er frLportPolVerTmr	5 30			
718 {	18) frLportDescrip	frLportCnfEntry.6	OctetString	read-write	mandatory

EXEMPLARY MIB TEXT FOR A FRAME-RELAY PORT

Figure 5

800

802 { FrameRelay Local Port Configure Slot 2 Port 1

804 { Frame Relay Local Port Configure Slot:  
• 2

806 { Frame Relay Local Port Configure Port:  
• 1

808 { Frame Relay Local Port Configure Clock Type:  
• [Normal]  
• Looped  
• None

810 { Frame Relay Local Port Configure Oper Status:  
• Inactive

812 { Frame Relay Local Port Configure Verification Timer:  
• 5  
• To change, enter new value in the range 5-30 and select Change  
•

814 { Frame Relay Local Port Configure Description:  
• IBM Mainframe Port  
• To change, enter a new string and select Change  
•

Figure 6